

# Set persistent MAC for RTL8111/8168/8411 (r8169) with udev

This tutorial does only work on systems that use **udev**, like IPFire!

The Linux kernel mod r8169 seems to set random MAC addresses for Realtek's ethernet cards 8111/8168/8411 every time this devices gets booted. This behaviour also seems to be intended like described in [this](#) kernel patch.

You can verify this by checking your (boot-) log, if it contains `can't read MAC address, setting random one` on the device that uses the mod r8169, you may be affected.

But it may break your system like when using IPFire that recognizes it's NICs from their MAC address.

## Get PCI device information

Use the following command and determine your NIC and it's PCI address: (pciutils is required)

```
lspci -v
```

The output may look like this:

```
04:00.0 Ethernet controller: Realtek Semiconductor Co., Ltd. RTL8111/8168/8411 PCI Express Gigabit Ethernet Controller (rev 15)
Flags: bus master, fast devsel, latency 0, IRQ 19
I/O ports at e000 [size=256]
Memory at f7304000 (64-bit, non-prefetchable) [size=4K]
Memory at f7300000 (64-bit, non-prefetchable) [size=16K]
Capabilities: <access denied>
Kernel driver in use: r8169
Kernel modules: r8169
```

Now take note of it's address, in this case 04:00.0.

## Create udev rules

Then add a udev-rule for this NIC. Therefore create a new rule:

```
nano /etc/udev/rules.d/10-network-persistent-custom-mac-address.rules
```

And add the following content:

```
SUBSYSTEM=="net", ACTION=="add", KERNELS=="0000:<pci-address>",
PROGRAM="/sbin/ip link set %k address <your-persistent-mac>"
```

Replace `pci-address` with the NICs PCI address that you got from the step before and `your-persistent-mac` with the MAC address that should always be assigned to this NIC. (both without `<` and `>`).

Finally save the file and reboot.

---

*Resourced used:* [serverfault.com - Change interface MAC HW address](#), [packetpushers.net - udev](#)

From:

<http://fixes.brecht-schule.hamburg/> - Fixes | Public BIT Wiki

Permanent link:

<http://fixes.brecht-schule.hamburg/linux/linux-tutorials/set-persistent-mac-rtl8111?rev=1702971542>

Last update: **2023/12/19 08:39**

